COMPAS Windows Installation

Install Windows Subsystem for Linux (WSL)

```
# Install in Windows Terminal as an administrator:
wsl --install
# Reboot system.
```

Install Ubuntu Distribution of Linux

```
# Install in Windows Terminal as an administrator:
wsl --install
# Create new user account.
```

Install Dependencies

```
# Update all Ubuntu repository package lists:
sudo apt-get update

# Install C++ compiler, and the boost, gsl, and hdf5 library packages.
sudo apt-get install g++ libboost-all-dev libgsl-dev libhdf5-dev
```

Clone COMPAS Code Repository

```
# Change to home directory:
cd ~

# Clone the COMPAS code repository:
git clone https://github.com/TeamCOMPAS/COMPAS
```

Define COMPAS Environment Variable

```
# Open bash file located in home directory (~/.bashrc) with Windows Notepad.
# Append the following:
export COMPAS_ROOT_DIR_=~/COMPAS

# Reload bash shell session:
source ~/.bashrc

# (Optional) Check if environment variable was correctly defined;
# Returns COMPAS root directory:
echo $COMPAS_ROOT_DIR
```

Build COMPAS

```
# (If Applicable) Open Makefile located in COMPAS source code directory
# (~/COMPAS/src) with Windows Notepad, and modify package directory paths.
#
# Most likely the only modification needed would be to the
# HDF5LIBDIR directory path, e.g.
# /usr/lib/x86_64-linux-qnu/hdf5/serial
# /usr/lib/aarch64-linux-gnu/hdf5/serial
# /usr/lib/<architecture>-linux-gnu/hdf5/serial
# (If Applicable) List the installed package directory paths:
dpkg -L libboost-all-dev
dpkg -L libgsl-dev
dpkg -L libhdf5-dev
# Install make command:
sudo apt install make
# Change to COMPAS source code directory:
cd $COMPAS_ROOT_DIR/src
# Clear preexisting builds of COMPAS:
make clean
```

```
# Build (Compile & Link) COMPAS:
make

# (Recommended) Build COMPAS using (4) simultaneous threads:
make -j4

# IMPORTANT: It is not recommended to build with more than 4 CPU threads
# since the compilation has high RAM consumption.
```

Running COMPAS

```
# COMPAS is a command-line application.
#
# COMPAS does not need to be rebuilt unless changes are made to the
# installed packages, or new updates for COMPAS are installed.
# Check current version:
./COMPAS -v
./COMPAS -v
./COMPAS --version
# List command-line options:
./COMPAS -h
# List command-line options w/brief descriptions:
./COMPAS --help
# Run default program with default parameters:
./COMPAS
```